


## Introduction

This is a quick guide intended for users who have installed both the latest version of Client License Manager and Infinity. At the time when this guide was written, the current version of the respective software is:

**CLM version 2.17.0**

**Leica Infinity version 4.1.4**

Beyond version 4.0.0 of Leica Infinity has highly improved the activation wizard to enable or find licensing.



The Activation Wizard allows to establish the licensing via one of three methods. These are:


1. **Case 1 - Activate License** - This method is the proper choice is the license is activated on the local computer.
2. **Case 2 - Connect to License Server** - This is the method if the licensing is activated on a server external to the local computer.
3. **Case 3 - Activate License Offline** - This is the method that is useful if the computer/server in which the license is to be activated does not have online access.

---


## Case 1 - Activate License

This first method is the case in which the license (Entitlement ID - EID) is activated on the local computer.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453




Select the box labeled "Activate License" illustrated above.




Notice that the minimum required license is indicated in the center of the display, but the Status is not available.

1. Press **Next** to continue.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453




1. Enter the Entitlement ID(s) to be activated in the **EID** field as shown above.
2. Press **Add** to continue with the activation.



Once the license is activated the wizard provides indication of success.

**Leica Licensing using Client License Manager**  
**Support Toll Free: (855) 414-9453**

1. Press **Exit** to complete the process. Infinity will now start.




Notice in the backstage of Infinity under **File/About** the details of the licensing are displayed. Notice that a Training EID was utilized for this example. It is the same process for any EID.


## Case 2 - Connect to License Server

This case illustrates how to connect to a license server from the workstation.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453




Select the box, **Connect to License Server** as illustrated above.




1. Enter the name of the server that you are connecting to. This would be the actual server name.
2. Press the red ball with the check mark

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453




1. Notice the indication that the **Server connection established**. If this is not the case, then verify the server name and try again. The local IT group may need to confirm that connection is possible if there are further issues.
2. Press **Done**



1. Confirmation of the server connection is confirmed. Press **Exit** and Infinity will start on the workstation.


## Case 3 - Activate License Offline

This case outlines the offline method of license activation. This is for cases in which either a server, or the workstation requires activation of a license that is not permitted to be connected to the internet. In the steps below there are two methods of obtaining the required files. These are via myWorld or email. The myWorld method does require that the Entitlement ID (EID) has been entered to the user's myProducts area. If the myWorld method has not been completed, then the email method should be considered the method of choice. The steps are outlined below.




Select the **Activate License Offline** box illustrated above.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453




1. After this check for featus/products panel press **Next** to continue.



## Leica Licensing using Client License Manager


Support Toll Free: (855) 414-9453

1. Initiate the process to generate the CLM Start file (\*.clmstart) by one of the two methods outlined above.
2. Press **Next** to continue.




1. Add the start file .clmstart file by either Drag and Drop or Browse to the file location on the system.
2. Press **Next** to continue. Note: the Next button is active once the file has been added in the following illustration.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453



1. Press **Next** to continue to initiate the creation of the request file.




1. The location of the request file is shown as illustrated above.

## Leica Licensing using Client License Manager


Support Toll Free: (855) 414-9453

2. Submit the request file (\*.clmreq) by one of the two methods listed above as before.
3. Press **Next** which will create the response file (\*.clmresp).




1. Add the response file (\*.clmresp) file by either Drag and Drop or Browse to the file location on the system.
2. Press **Next** to continue. Note: the Next button is active once the file has been added as indicated in the following illustration.

## Leica Licensing using Client License Manager Support Toll Free: (855) 414-9453



1. Press **Add** to complete the process.



1. There is indication that the activation was successful. Press **Exit** to close the Activation wizard.